

# Set up your email client/phone for Ivuenet.com:

1. Open your e-mail client software or Phone mail settings.
2. Click the **Tools** menu, and select **E-mail Accounts...**
3. Click **Add a new e-mail account**, and click **Next**.
4. Choose **POP3** as your server type by clicking the radio button, and click **Next**.
5. Fill in all necessary fields to include the following information:

## User Information

**Your Name:** Enter your name as you would like it to appear in the **From:** field of outgoing messages.

**Email Address:** Enter your full email address (*username@lvuenet.com*)

## Server Information

**Incoming mail server (POP3):** pop.gmail.com

**Outgoing mail server (SMTP):** smtp.gmail.com

## Login Information

**User Name:** Enter your full email address (*username@lvuenet.com*)

**Password:** Enter your email password

**E-mail Accounts**

**Internet E-mail Settings (POP3)**  
Each of these settings are required to get your e-mail account working.

**User Information**

Your Name: Nathan Woodward  
E-mail Address: nanowoodward@gmail.com

**Server Information**

Incoming mail server (POP3): pop.gmail.com  
Outgoing mail server (SMTP): smtp.gmail.com

**Logon Information**

User Name: nanowoodward@gmail.com  
Password: \*\*\*\*\*  
 Remember password  
 Log on using Secure Password Authentication (SPA)

**Test Settings**

After filling out the information on this screen, we recommend you test your account by clicking the button below. (Requires network connection)

Test Account Settings ...  
More Settings ...


< Back   Next >   Cancel

6. Click **More Settings...** and then click the **Outgoing Server** tab.

7. Check the box next to **My outgoing server (SMTP) requires authentication** and select **Use same settings as my incoming mail server**.



- Click the **Advanced** tab, and check the box next to **This server requires an encrypted connection (SSL)** under **Incoming Server (POP3)**.



- Check the box next to **This server requires an encrypted connection (SSL)** under **Outgoing Server (SMTP)**, and enter 465 in the **Outgoing server (SMTP)** box.
- Click **OK**.
- Click **Test Account Settings...** After receiving **Congratulations! All tests completed successfully**, click **Close**.
- Click **Next**, and then click **Finish**.

**Congratulations!** You're done configuring your lvenet.com email account.